ubuntu drupal

Setup Guide: UD Header

Table of Contents

Installation

To install the module, I will assume you already followed the UD Theme installation guide. From the front page click "Administer."

In the "Site Building" section click "Modules."

You will then be looking at the modules page.

Scroll down to the bottom of the page to see the "Ubuntu Drupal" group of modules.

Select the "UD Header" module and click "Save Configuration."

Configuration

Go to the "Administration" page.

Click the "UD Header Settings" link.

You will see the header maps as well as a section to add header mappings.

Add Header

To add a header mapping, follow the above and expand the "Header" section.

▽ **Add Header**

Node Type:

Feed ▼

Select the node type which the header will be applied for.

Left Image:

docs.jpg ▼

Select the image to be used on the left side of the header.

Center Image:

center.png ▼

Select the image to be used in the center of the header.

Text to be displayed in the center of the masthead:

Right Image:

red.png ▼

Select the image to be used on the right side of the header.

Text to be displayed in the right part of the masthead:

Add

The following is just an example of some content. After filling in information, just click "Add."

▽   **Add Header**

Node Type:

Default   ▼

Select the node type which the header will be applied for.

Left Image:

docs.jpg   ▼

Select the image to be used on the left side of the header.

Center Image:

center.png   ▼

Select the image to be used in the center of the header.

Text to be displayed in the center of the masthead:

```
<h1>Welcome to the Ubuntu Drupal testing website!</h1>
```

Right Image:

yellow-logo.png   ▼

Select the image to be used on the right side of the header.

Text to be displayed in the right part of the masthead:

```
<a href="https://launchpad.net/ubuntu-drupal">Learn more</a> about our tools.
```

Add

Edit / Delete Header

To alter a header mapping, click the "edit" link to the right of the mapping you want to edit.

▷ Add Header

HEADER MAPS

Node Type	Left Image	Center Image	Right Image	Edit
udheader_default	docs.jpg	center.png	yellow-logo.png	edit

If you want to make changes, you can make them and click Update. If you want to delete the box, click Delete.

Update   Delete

Configure the Block

To configure the block so id displays on your site, go to the "Administration" page and click the "Blocks" link in the "Site Building" section.

Site building
Control how your site looks and feels.

Blocks
Configure what block content appears in your site's sidebars and other regions.

Menus

Find the "Ubuntu Drupal Header" block. Select the drop down box to the right of it that currently says "None" and select a region for it. For the example, we will use the "Header" region.

Ubuntu Drupal Header   \<none>   configure

You will see the module was moved into this section (region). You can use the handle to adjust its exact location.

Header
Ubuntu Drupal Header*   Header   configure

Scroll down to the bottom and click "Save Configuration." After this saves, go to your front page.

Save blocks

You will now see the block content displayed where you assigned it.

loco team
staging.profarius.com
SLOGAN SLOGAN SLOGAN SLOGAN SLOGAN SLOGAN SLOGAN SLOGAN SLOGAN SLOGAN

Welcome to the Ubuntu Drupal testing website!   Learn more about our tools.

MTECKNOLOGY
○ My account   HOME

Permissions

This module has permission settings just like any other module. To get to these permissions, go to the "Administration" page and click the "Permissions" link.

This page is well constructed and well documented in other places. This guide has an example of a basic set of permissions. You can copy these, click "Save Permissions" and tweak as you please.

Permission	anonymous user	authenticated user	administrative user
udcountdown module			
administer udcountdown	☐	☐	☑
view udcountdown	☑	☑	☑
udheader module			
administer udheader	☐	☐	☑
view udheader	☑	☑	☑
udplanet module			
administer own feeds	☐	☑	☑
administer udplanet	☐	☐	☑
view udplanet	☑	☑	☑
udsidebar module			
administer udsidebar	☐	☐	☑
view udsidebar	☑	☑	☑

Save permissions